

# (Pour information) GLPI - configurer l'API REST

Liens :

- <https://docs.ametys.org/fr/plugins/glpi/v1/manuel-d-administration.html>
- <https://tic.gal/en/how-to-setup-glpi-api/>

## Activation de l'API REST

- se rendre dans le menu **Configuration > Générale** et choisir la rubrique **API** ;
- Choisir **Activez l'API REST** ;
- Cochez **Activez la connexion avec un jeton externe** ;
- Cliquez sur **Sauvegardez**.

The screenshot shows the GLPI configuration interface. The top navigation bar has tabs for Parc, Assistance, Gestion, Outils, Administration, and Configuration. The Configuration tab is selected and highlighted with a blue border. Below the tabs, there's a breadcrumb navigation: Accueil > Configuration > Générale. A yellow arrow points to the 'Générale' tab. On the left, a sidebar lists various configuration categories: Configuration générale, Valeurs par défaut, Parc, Assistance, Purge de l'historique, Système, Sécurité, and Performance. The main content area is titled 'API'. It contains fields for 'URL de l'API' (set to 'http://localhost/glpi/apirest.php') and two dropdowns: 'Activer l'API Rest' (set to 'Oui') and 'Activer la connexion avec identifiants' (set to 'Non'). Another dropdown 'Activer la connexion avec un jeton externe' is also set to 'Oui'. A large orange 'Sauvegarder' button is at the bottom. The status bar at the bottom right shows 'Page courante en PDF paysage'.

## Ajouter un client API

Par défaut, l'API GLPI autorise uniquement les accès depuis le serveur lui-même : **full access from localhost**

The screenshot shows the GLPI interface for managing API clients. The top navigation bar includes links for Parc, Assistance, Gestion, Outils, Administration, Configuration, and a search bar. The main menu path is Accueil > Configuration > Générale > Clients de l'API. A specific client entry, "full access from localhost [Entité ra...]", is selected and highlighted with a red box. The client details show it is an "Entité racine" (Root entity) with "Sous-entités" set to "Oui". The "Nom" field contains "full access from localhost". The "Actif" (Active) status is "Oui", and "Enregistrer les connexions" (Register connections) is set to "Désactivé" (Disabled). Below the client details, there is a section for "Filtrer l'accès" (Filter access) with a note: "Laisser ces paramètres vides pour désactiver la restriction d'accès à l'API". This section includes fields for "plage d'adresses IPv4" (IP range) set to "127.0.0.1" and "127.0.0.1", "adresse IPv6" (IPv6 address) set to "::1", and a "Jeton d'application (app\_token)" field with a "Regénérer" (Generate again) checkbox. At the bottom right of the client card are buttons for "Sauvegarder" (Save) and "Supprimer définitivement" (Permanently delete).

Il est donc nécessaire de **créer un client d'API** :

- en indiquant la **plage d'adresses IP** autorisées à accéder à l'API ;
- en générant un **jeton d'application (app\_token)**.

## Retour Activité A8

- A8 - La gestion des configurations avec GLPI

From:  
[/- Les cours du BTS SIO](#)

Permanent link:  
[/doku.php/si7/configuration/glpi\\_configapiglpi?rev=1614623958](/doku.php/si7/configuration/glpi_configapiglpi?rev=1614623958)

Last update: **2021/03/01 19:39**

